

Navigation

- [Main page](#)
- [Recent changes](#)
- [Random page](#)
- [Help about MediaWiki](#)

Tools

- [What links here](#)
- [Related changes](#)
- [Special pages](#)
- [Permanent link](#)
- [Page information](#)

Personal tools

- [Log in](#)

personal-extra

Views

- [View](#)
- [View source](#)
- [History](#)
- [PDF Export](#)

Actions

Template:Flex columns

From Blue Gold Program Wiki

The printable version is no longer supported and may have rendering errors. Please update your browser bookmarks and please use the default browser print function instead.

This template is used on [approximately 4,800 pages](#) and changes may be widely noticed. Test changes in the template's [/sandbox](#) or [/testcases](#) subpages, or in your own [user subpage](#). Consider discussing changes on the [talk page](#) before implementing them.

This template uses [Lua](#):

- [Module:Flex columns](#)

This template uses [TemplateStyles](#):

- [Template:Flex columns/styles.css](#)

This template creates a column layout, where contents within the columns will have the same height, with any extra whitespace distributed throughout the shorter columns contents. It is mainly intended for use in portals.

This sort of layout requires browsers to support [CSS flexbox](#). For those that don't there is a fallback that will show a two column view, but without the heights being the same (a layout many portals used as at July 2018).

For narrow screens, e.g. mobile devices, the display reverts to a single column.

Usage

```
{{Flex columns
|1 = (...first column contents...)
|2 = (...second column contents...)
}}
```


Only contents which are in `<div>...</div>` tags will have extra whitespace distributed to them - except for those with class `flex-columns-noflex` (or otherwise override the `flex:` property)

To change the column balance, `|flex1=` and/or `|flex2=` can be set. The default for each is 1. For example:

- `|flex1=3 |flex2=2` will result in the first column taking up to 60% (3/5) of the available width, and the second column taking up at least 40% (2/5) of the width.

Note that the actual column balance will vary depending on screen size, since the minimum width of each column is set at 360px.

See also



The above [documentation](#) is [transcluded](#) from [Template:Flex columns/doc](#). ([edit](#) | [history](#))
Editors can experiment in this template's [sandbox](#) ([create](#) | [mirror](#)) and [testcases](#) ([create](#)) pages.
Add categories to the [/doc](#) subpage. [Subpages of this template](#).

Retrieved from

"https://www.bluegoldwiki.com/index.php?title=Template:Flex_columns&oldid=2233"

Namespaces

- [Template](#)
- [Discussion](#)

Variants

[Categories:](#)

- [Pages with broken file links](#)
- [Lua-based templates](#)
- [Templates using TemplateStyles](#)

This page was last edited on 26 April 2020, at 05:11.

Blue Gold Program Wiki

The wiki version of the Lessons Learnt Report of the Blue Gold program, documents the experiences of a technical assistance (TA) team working in a development project implemented by the Bangladesh Water Development Board (BWDB) and the Department of Agricultural Extension (DAE) over an eight+ year period from March 2013 to December 2021. The wiki lessons learnt report (LLR) is intended to complement the BWDB and DAE project completion reports (PCRs), with the aim of recording lessons learnt for use in the design and implementation of future interventions in the coastal zone.

- [Privacy policy](#)
- [About Blue Gold Program Wiki](#)
- [Disclaimers](#)

Developed and maintained by Big Blue Communications for Blue Gold Program



[Blue Gold Program Wiki](#)